

---

# How To Screenshot On Windows 7

---

*How To Screenshot On  
Windows 7*

*Downloaded from [turn-nyc-  
edge-vdmdp.louper.io](https://turn-nyc-edge-vdmdp.louper.io) by  
Sherlyn & Salazar*

---

## MASTERING SCREENSHOTS ON WINDOWS 7: A COMPLETE GUIDE

---

Capturing what is on your screen is one of the most useful skills you can learn on a computer. Whether you need to save a fleeting error message, share a funny moment from a video call, or document an important piece of information, knowing how to screenshot on Windows 7 can save you time and frustration. Even though Windows 7 is an older

operating system, it still offers several reliable methods to take a picture of your screen. In this guide, we will walk you through every technique, from the classic Print Screen button to the built-in Snipping Tool and a few third-party options. By the end, you will be able to capture exactly what you need with confidence.

## Why Screenshots

# Matter in Daily Computer Use

Before diving into the steps, it is worth understanding why screenshots remain essential. They allow you to capture visual information that cannot be easily described in words. For example, a screenshot of a software bug can help a technician understand the problem instantly. In work environments, screenshots are used to create training materials, document progress, or share design mockups. For students, taking a snapshot of an online lecture slide can be a quick way to review later. Knowing how to screenshot on Windows 7 empowers you to communicate more

effectively and preserve important moments.

---

## METHOD 1: USING THE PRINT SCREEN KEY (PRTSCN)

---

The most straightforward way to take a screenshot on Windows 7 is by using the **Print Screen** key, often labeled *PrtScn*, *PrtSc*, or something similar on your keyboard. This method has been a staple of Windows for decades, and it works without any extra software installed.

## Capturing the Full Screen

To capture everything visible on your monitor, simply press the **PrtScn** key.

Nothing will appear to happen, but the screenshot is stored on your clipboard. You then need to paste it into an image editing program, such as **Microsoft Paint**, which comes preinstalled with Windows 7.

1. Press the **PrtScn** key once.
2. Open **Paint** by clicking the Start button, typing *Paint* in the search box, and selecting it.
3. Click the **Paste** button in the top-left corner, or press **Ctrl + V** on your keyboard.
4. Your screenshot will appear. You can now save it by clicking **File > Save As** and choosing a format (PNG is recommended for quality).

This method is ideal when you need an exact copy of your entire desktop,

including all open windows and the taskbar.

## Capturing Only the Active Window

Often you do not need the entire screen—just the window you are currently using. Windows 7 makes this easy with a handy shortcut: **Alt + PrtScn**. This captures only the active window (the one with the highlighted title bar) and copies it to the clipboard.

- Click the window you want to capture to make it active.
- Press **Alt + PrtScn**

simultaneously.

- Paste the image into Paint or another program as described above.
- Save the file.

This is perfect for capturing a dialog box, a web page, or a single application without including your desktop background or other open programs.

## Using the Windows Key + PrtScn Shortcut

### (If Available)

Some keyboards and driver configurations on Windows 7 may support the **Windows key + PrtScn** shortcut. This combination does two things: it captures the full screen and automatically saves the image as a PNG file. The file is stored in the **Screenshots** folder inside your **Pictures** library. However, this feature was introduced more prominently in Windows 8 and later, so it may not work on all Windows 7 systems. It is worth trying: press both keys together, then look in *Pictures > Screenshots*. If you find the image there, you have a quick one-step method.

## METHOD 2: THE SNIPPING TOOL

Windows 7 includes a hidden gem called the **Snipping Tool**. Unlike the Print Screen key, the Snipping Tool gives you control over which part of the screen to capture. It also allows you to add annotations, save files directly, and even set a time delay.

# How to Open the Snipping Tool

Click the **Start** button, type *Snipping Tool* in the search box, and press Enter. If you use it frequently, you can right-click its icon and choose **Pin to Taskbar** for quick access.

## Capture Modes Explained

The Snipping Tool offers four capture modes:

- **Free-form Snip:** Draw any shape around the area you want to capture.
- **Rectangular Snip:** Click and drag to create a perfect rectangle.
- **Window Snip:** Select an open window (such as a browser or document) to capture it instantly.
- **Full-screen Snip:** Captures the entire screen, similar to pressing PrtScn.

To take a screenshot:

1. Open the Snipping Tool.
2. Click the arrow next to **New** to choose your snip type, or just click **New** if you want the default rectangular snip.
3. Select the area on your screen. The screen will fade slightly to help you see your selection.
4. Once you release the mouse button, the snip opens in a new window.
5. You can highlight, pen, or erase parts of the image using the toolbar.
6. Click the **Save Snip** icon (floppy disk) to save the image in your desired format.

## Adding a Delay

The Snipping Tool in Windows 7 also has a **Delay** feature. This allows you to capture menus or tooltips that disappear when you click elsewhere. After opening the tool, click the **Delay** button and choose a number (e.g., 3 seconds). Then click **New**, and the tool will wait the specified time before the screen freezes. This gives you time to open a context menu or hover over a button before the capture occurs.

---

### METHOD 3: USING THE ON-SCREEN KEYBOARD

---

If your physical keyboard is missing the Print Screen key or you are using a tablet or laptop where the key functions

differently, you can use the **On-Screen Keyboard** built into Windows 7. This virtual keyboard includes all the standard keys, including **PrtScn**.

1. Click **Start**, type *On-Screen Keyboard*, and press Enter.
2. A keyboard will appear on your screen. Locate the **PrtScn** key (usually on the right side).
3. Click it to capture the full screen. For the active window only, hold the **Alt** key on your physical keyboard and then click **PrtScn** on the virtual keyboard.
4. Paste the screenshot into Paint or another program.

This method is especially useful for those with accessibility needs or limited keyboard functionality.

---

## METHOD 4: THIRD-PARTY SCREEN CAPTURE TOOLS FOR WINDOWS 7

---

While built-in tools work well, some users prefer additional features like scrolling captures, screen recording, or direct sharing. Several free and paid programs are compatible with Windows 7.

### LightShot

LightShot is a lightweight tool that lets you select any area of the screen and save or share it instantly. After installation, pressing the **Print Screen** key brings up a crosshair to choose your region. You can then annotate, upload to the cloud, or copy the image.

# Greenshot

Greenshot is an open-source tool that offers even more flexibility. It supports capturing a region, window, or full screen. It also includes an editor for adding arrows, text, and highlights. Greenshot can export directly to a file, printer, email, or even Microsoft Office programs. It runs smoothly on Windows 7.

# PicPick

PicPick combines a screen capture tool with a simple image editor and color picker. The free version is sufficient for most users. You can customize hotkeys and choose from multiple capture

modes.

# Snagit (Paid)

For professional use, Snagit by TechSmith is a powerful option. It includes video recording, scrolling window captures, and advanced editing features. It works on Windows 7, but note that newer versions may have dropped support. Check compatibility before purchasing.

Third-party tools often save you the step of pasting into Paint, as they allow direct saving with a single click. They are worth considering if you take screenshots frequently.

---

**WHERE WINDOWS 7 SAVES YOUR**

## SCREENSHOTS

---

Understanding where your screenshots are stored helps you find them later. The methods above behave differently:

- **Print Screen (PrtScn)** and **Alt + PrtScn**: Screenshots go to the clipboard only. You must paste and save them manually. They are not saved automatically.
- **Windows Key + PrtScn** (if supported): Saves automatically to `C:\Users\YourUserName\Pictures\Screenshots`.
- **Snipping Tool**: You choose the save location when you click **Save Snip**. If you close the tool without saving, the screenshot is lost.
- **Third-party tools**: Usually save to a predefined folder, often *My*

*Documents* or a specific tool folder. Check the settings to customize.

To avoid losing your captures, develop a habit of saving immediately after pasting or using the Snipping Tool's save prompt.

---

## EDITING AND ANNOTATING SCREENSHOTS ON WINDOWS 7

---

Once you have a screenshot, you might need to add arrows, text, or highlight important areas. Windows 7's **Paint** program is capable of basic editing, but it lacks modern annotation tools. For simple tasks, you can use the **Shapes** (like rectangles or lines) and the **Text** tool in Paint. For more advanced needs, consider using the free **GIMP** (GNU

Image Manipulation Program) or the built-in editing features of third-party capture tools like Greenshot or PicPick.

The Snipping Tool also includes a pen, highlighter, and eraser, which are sufficient for quick annotations. To use them, select the tool from the toolbar that appears after you take the snip.

---

## COMMON ISSUES AND TROUBLESHOOTING TIPS

---

Even simple tasks can sometimes go wrong. Here are a few frequent problems and their solutions when trying to screenshot on Windows 7:

- **Print Screen does nothing:**

Make sure you are pressing the correct key. On some laptops, you might need to hold the **Fn**

(Function) key while pressing **PrtScn**. Also, if you have clipboard management software, it might interfere. Try disabling it temporarily.

- **Pasted image is black or blank:**

This can happen if you try to capture a video playback that uses hardware acceleration. Try disabling hardware acceleration in your media player or browser, or use the Snipping Tool instead.

- **Snipping Tool not available:**

Some editions of Windows 7 (like Starter or Home Basic) do not include the Snipping Tool. In that case, use the Print Screen method or download a third-party tool.

- **Cannot find saved screenshots:**

Double-check the folder you saved

to. If you used the clipboard